

Kennisbank > Pagina's en producten > How to set Product Price up to 3 decimal places

How to set Product Price up to 3 decimal places

Elenor A. - 2021-11-26 - Pagina's en producten

How to set Product Price up to 3 decimal places

To set the currency format into 3 decimal places for "Product Price" you need to do the following -

- Go to Control Panel
- Double click "Regional and Language Options"
- At the Regional Options tab, click "Additional settings..." button
- And then click the "Currency" tab
- Click drop down button at the "No. of digits after decimal"

🚱 Region	×	Dustomize Format	×
Formats Administrative	3	Nurvers Currency Time Date	
Format: English (United States)		Example	-1
Match Windows display language (recommended)		Positive: \$123,456,789.00 Negative: (\$123,456,789.00)	
Language preference	es		- 1
Date and time formats		Currency symbol:	
Short date:	M/d/yyyy ~	Currency symbol:	
Long date:	dddd, MMMM d, yyyy	Positive currency format: \$1.1 \virtual states and stat	
Short time:	h:mm tt 🗸 🗸	Negative currency format: (\$1.1) ~	
Long time:	h:mm:ss tt 🗸 🗸		
First day of week:	Sunday ~	Decimal symbol:	
		No. of digits after decimal: 3	3
Examples		0	
Short date:	11/26/2021	Digit grouping symbol: 2	
Long date:	Friday, November 26, 2021	Digit grouping:	
Short time:	2:12 PM	5 6	
Long time:	2:12:46 PM	7	
	Additional settings	8 9	
	OK Cancel Apply	Click Reset to restore the system default settings for numbers, currency, time, and date.	
		OK Cancel Ap	oply

- Click OK

- Click OK

Then you need to update the CURRENCY.XML file manually:

The changes to currency.xml are not checked into SF. This needs to be done manually by the merchant because if it was in there by default, then prices will have 3 decimal places for all ShopFactory users, which is not the usual case. Most merchants only use the 2 decimal places format.

Edit the currency.xml file in SF for this to take effect.

- Edit the currency.xml so that the currency has the "SignificantDigits" attribute set to 3.
- Open Windows Explorer and at the "Address: " bar, type

C:\Program Files (x86)\ShopFactory V14\ShopFactory\

- Press ENTER key from your keyboard.
- At the contents pane, locate the file called "Currency.xml"
- Right-click on the Currency.xml file and from the shortcut menu, select Open With...-> Notepad.
- The Currency.xml file will show in Notepad as plain text.
- Press CTRL + F and type EUR or whatever your currency is
- Click NEXT and edit ALL SignificantDigits instances to 3
- Find "EUR", for example -> then change the value at SignificantDigits=""
- Click "Find Next" until all the instance has been changed accordingly, such as "EUR" SignificantDigits="3"
- Once finished, close Notepad.

- open the shop project in SF and re-select the currency in "Central dropdown -> Currencies accepted" for this to take effect.

- enter the price with 3 decimal places
- Save and preview shop.